

sparklestock[★]

RETRO PHOTOKIT

15 Retro Film Photoshop Actions, 10 Light Leaks,
Date Stamp Generator and Date Stamp Font

A Great Big Thank You!

Thank you for your purchase! Here's how to get started:

Loading the Photoshop Actions:

1. Extract the ZIP file.
2. In Photoshop, open the Actions panel (Window > Actions).
3. Choose the ATN file with a filename that matches your version of Photoshop. Drag and drop the ATN file into the Actions panel.
4. Select an action and click the play button.

Can't find the download?

1. Open the Creative Cloud desktop application, click the three vertical dots icon in the upper-right, and then select Preferences.
2. Click Creative Cloud and select Files. Ensure that File Sync is enabled.

Using the Retro Film Actions:

1. In the Actions panel (Window > Actions), click on the "Play All Effects" action.
2. Go into your History panel (Window > History) and select an effect.
3. Adjust the layer opacity to change the strength of the effects.

Using the Date Stamp Actions:

1. In the Actions panel (Window > Actions), click on the Step 1 action that corresponds with the orientation of your document. For example, if your document is horizontal/landscape, play the "Horizontal Photos - Step 1" action.
2. Select the Text tool (T) to edit the text. We recommend using the "Date Stamp" font that comes with your purchase. For an authentic date stamp look, use the "Date Stamp Alt" font. This font positions the letter as they would be displayed on a real LCD. You can choose any font size but for an authentic look, choose a font size that matches the height of the two blue lines.
3. Play the "Step 2" action.
4. If you are using a high-res photo, you can add a slight blur to the date stamp. Simply doubleclick on the Gaussian Blur smart filter located under the Date Stamp layer then edit the blur setting.

Using the Light Leaks:

1. Drag and drop (or go to File > Place) any light leak image into your document.
2. Change the blending mode to Linear Dodge. You can also experiment with other blending modes such as Screen, Overlay, Linear Light, etc.

Video Demo:

<https://youtu.be/fOyD9wBp0zA>

FAQ:

Q: Why am I getting a command "If" error message?

A: Please remove the actions from your panel and load the Photoshop CS6 ATN file (Not the Photoshop CC version).

Q: I am getting error messages. How do I fix this?

A: Please go to Image > Mode and ensure that your image is in 8-bit RGB mode.



We're happy to help you!
Contact us at support@sparklestock.com

sparklestock[★]