
WP-Exporter 1.0.0 Guide © 2020 Oussama Touzni



Introduction

In this document I'm going to guide you through the installation process of WP-Exporter 1.0, then I'll explain the basic configuration of the plugin and how to get the most of it!

How to install:

Download the ZXP file and use ZXPInstaller (https://install.anastasiy.com/) or Anastasiy's Extension Manager (https://install.anastasiy.com/) and follow the instructions to install the plugin.

If for any reason the installation fails, you can change the extension of the downloaded archive to zip and extract it to one of the following folders:

For Windows users:

Win(x86): C:\Program Files\Common Files\Adobe\CEP\extensions

For Mac users:

/Library/Application Support/Adobe/CEP/extensions

After installing the extension, please follow these steps:

Know your CEP supported version:

Application	2017	2018	2019	CC 2020
	Version	Version	Version	Version
Adobe InDesign	12 (CEP 7)	13 (CEP 8)	14 (CEP 9)	15 (CEP 9)

For windows users:

Download the corresponding file to your installed product https://drive.google.com/open?id=1QVSX AMOku9f-9d TSC118V5q5jqAZTI

For example, if you're using Adobe InDesign 2018, download Debug Mode ON CEP 8.reg and execute it and that should be all!

For Mac users:

Execute one of the following commands depending on your CEP version:

Version	command
CEP 7	defaults write com.adobe.CSXS.7 PlayerDebugMode 1
CEP 8	defaults write com.adobe.CSXS.8 PlayerDebugMode 1
CEP 9	defaults write com.adobe.CSXS.9 PlayerDebugMode 1

WordPress Configuration

The REST-API must be activated on your WordPress blog to use WP-Exporter.

You may encounter some issues with the authentication depending on your WordPress version and your website host , some of the fixes are :

- 1- Installing a plugin, we recommend using WP API SwaggerUI simply install and activate the plugin.
- 2- If you're still having problems add the following lines after #END WordPress in your .htaccess file

```
RewriteCond %{HTTP:Authorization} ^(.*)
RewriteRule ^(.*) - [E=HTTP_AUTHORIZATION:%1]
SetEnvIf Authorization "(.*)" HTTP_AUTHORIZATION=$1
```


If you followed everything and still can't get WP-Exporter to work, don't hesitate to contact me on "oussama.touzni@gmail.com" or contact@it-tun.com and specify "WP-Exporter Support" as subject so I can get back to you as soon as possible.

Users' configuration


WP-Exporter can be used with multiple WordPress blogs and many user accounts on the same blog, simply configure your websites/users and then choose which one to work with in the current session. You can switch between users with a simple click. Watch the following video for more details

https://youtu.be/STt_vl1k--E

Interfaces explained




- 1.Connected user avatar & username
- 2. Visit current WordPress blog
- 3. Quick support email
- 4.WordPress Categories list
- 5. Active document' articles List.
- 6.Refresh articles' List.
- 7. Article configuration state indicator.
- 8. Show article configuration modal.
- 9.General tags: will be applied to all the articles.
- 10. Tagging mode: off (raw content) / user defined: user tags are applied when exporting the article
- 11.Images' positioning
- 12.Start export button



Pink indicator: no configuration defined

Blue indicator: configuration loaded and not edited in the current session

Green: indicator: configuration changed during the active session



- 1-Article title
- 2-Featured image selection
- 3-Publishing status
- 4-Article related tags

How to use

Please watch the following tutorials: https://youtu.be/Exq3W9YURwQ

https://youtu.be/pYpRCQQc-U0

Thanks for putting your trust in our product, more information will be available soon on https://ittun.com/, if you need and help please don't hesitate to contact me on "oussama.touzni@gmail.com" or contact@it-tun.com and specify "WP-Exporter Support" as subject so I can get back to you as soon as possible.